

GGZ Gaming Zone Client/Game Client Protocol Specification

The GGZ Gaming Zone developers

`ggz-dev@mail.ggzgamingzone.org`

GGZ Gaming Zone Client/Game Client Protocol Specification
by The GGZ Gaming Zone developers

Copyright © 2005 The GGZ Gaming Zone developers

Module protocol specification for GGZ Gaming Zone game clients. This document covers the communication between the GGZ core clients and the game client modules.

Revision History

Revision \$Revision: 7521 \$ \$Date: 2005-09-16 23:43:09 +0200 (Fr, 16 Sep 2005) \$

Table of Contents

Objectives.....	v
1. The Protocol	1
Startup.....	1
Connected phase	1
Pregame phase.....	1
Playing phase.....	1
Done phase.....	2
A. Protocol Reference.....	3
Messages from the core client to game client.....	3
GAME_LAUNCH.....	3
GAME_SERVER.....	3
GAME_SERVER_FD	4
GAME_PLAYER	5
GAME_SEAT	5
GAME_SPECTATOR_SEAT	6
GAME_CHAT	7
GAME_STATS	7
GAME_INFO.....	8
Messages from game client to core client	9
GAME_STATE.....	9
STAND	9
SIT	10
BOOT	10
BOT	11
OPEN	12
CHAT.....	12
INFO	13
Symbolic identifiers and their values	14
ControlToTable	14
TableToControl	14
GGZSeatType	15
GGZModState	15

Objectives

A game client, when launched by a GGZ Gaming Zone core client such as `kggz` or `ggz-gtk`, will hold a connection to its launcher which is used to get the initial table layout, send out table chat, request seat changes and read a player's game records. This protocol is called the Client/Game Client Protocol, and is available in a reference implementation named `libggzmod`, written in the C programming language, and its wrappers for C++ and Python.

Objectives

Chapter 1. The Protocol

Communication between client and game client happens by means of binary tokens (opcodes), which are of type integer, followed by zero or more opcode-specific variables which can be of type integer, character, or string.

At each point in time, a game client happens to be in a specific state. Messages received from the core client may lead to state changes, as may some explicit transitions being executed by the game client itself. A list of all states can be found in the appendix of states.

Several actions refer to seats on the table the game is being played on. Each seat can be either empty or have an assignment. A full list can be found in the appendix of seat assignments.

Interactions are presented here categorically. For a complete reference of game client/core client interactions, please see the appendix of messages.

Startup

Each game client starts up in CREATED mode. In this step there is no information about seats or players yet. The only useful action is to wait for a GAME_LAUNCH message so the transition to the CONNECTED state can happen. Games can query whether they run on GGZ or not via the environment variable GGZMODE.

In order to carry out the transition to CONNECTED, the game client must connect to the core client. It does so by reading out the value of the environment variable GGZSOCKET, and then either uses this value as file descriptor, or (if no sockets can be passed directly) as local port to connect to. In the former case, GGZSOCKET defaults to the value 103.

Connected phase

When in CONNECTED state, a game client still isn't operable. There is another mandatory transition it has to do, namely to the WAITING state. This happens once the core client tells it where to connect to with a GAME_SERVER message, and that connections could be established without problems. Alternatively, depending on the operating system, the core client will establish the connection to the game server and pass it to the game client with a GAME_SERVER_FD message, so it can be used from the start on.

Pregame phase

Now that the game client is in WAITING state, it is fully operational and connected to the game server. The game server will receive player join events, until the game can start. This transition leads to the PLAYING state.

Playing phase

The PLAYING state is fully under the control of the game client. Messages to request seat changes might be sent from it to the core client, as might chat messages which are then sent to all other players on the table. Likewise, more information about the other players can be requested with an INFO request, upon a GAME_INFO message informs about those details. Not tied to a specific request but rather sent implicitly is the GAME_STATS message which contains statistical information about all registered players.

In case of a leaving player, the game client can change the state back to WAITING, and then forward to PLAYING again at any time. Once the game is finished, the (last) transition is done and leads to the DONE state.

Done phase

Once a game has reached the DONE state, there's no way back anymore. It will be destroyed and the corresponding table removed.

Appendix A. Protocol Reference

Messages from the core client to game client

GAME_LAUNCH

Name

GAME_LAUNCH — Initializes the game client

Synopsis

GAME_LAUNCH ...		
<i>Data</i>	<i>Type</i>	<i>Example</i>
Opcode	ControlToTable	GAME_LAUNCH

Description

This message is always the first one sent to the game client in order to initialize it. It will cause the transition from CREATED to CONNECTED state.

Message Data

None

Usage

This message only appears during the CREATED state.

GAME_SERVER

Name

GAME_SERVER — Tells the game where to connect to

Synopsis

GAME_SERVER ...		
<i>Data</i>	<i>Type</i>	<i>Example</i>
Opcode	ControlToTable	GAME_SERVER
Hostname	string	live.ggzgamingzone.org

Port number	integer	5688
Player handle	string	player42

Description

Tells the game where to connect to. This happens when the core client does not establish the connection (channel) to the game server first, as it would send a GAME_SERVER_FD in this case. The message causes a transition from CONNECTED to WAITING state.

Message Data

None

Usage

This message only appears during the CONNECTED state.

GAME_SERVER_FD

Name

GAME_SERVER_FD — Informs the game client about its connection to the game server

Synopsis

GAME_SERVER_FD ...		
<i>Data</i>	<i>Type</i>	<i>Example</i>
Opcode	ControlToTable	GAME_SERVER_FD
File descriptor	integer	3

Description

Depending on the operating system support, core clients can establish the connection to the game servers and pass this connection to the game clients once they're started and in the CONNECTED phase. Otherwise, GAME_SERVER will be sent to let the game client establish the connection. The message causes a transition from CONNECTED to WAITING state.

Message Data

None

Usage

This message only appears during the CONNECTED state.

GAME_PLAYER**Name**

GAME_PLAYER — Assigns the player's seat on the table

Synopsis

GAME_PLAYER ...		
<i>Data</i>	<i>Type</i>	<i>Example</i>
Opcode	ControlToTable	GAME_PLAYER
Player name	string	player42
Is player spectator?	integer/boolean	0
Seat number	integer	1

Description

Assigns the player's seat on the table. While usually GAME_SEAT and GAME_SPECTATOR_SEAT messages inform about seat assignments, this special message informs about the player's own seat so that the game can already arrange its settings early on.

Message Data

None

Usage

This message only appears during the WAITING state.

GAME_SEAT**Name**

GAME_SEAT — Assigns one single seat on the table

Synopsis

GAME_SEAT ...		
<i>Data</i>	<i>Type</i>	<i>Example</i>
Opcode	ControlToTable	GAME_SEAT
Seat number	integer	2
Seat type	GGZSeatType	0
Player name	string	player99

Description

A single seat assignment or a change thereof is communicated by this message.

Message Data

None

Usage

This message appears during the WAITING or PLAYING state.

GAME_SPECTATOR_SEAT

Name

GAME_SPECTATOR_SEAT — Assigns one single spectator seat on the table

Synopsis

GAME_SPECTATOR_SEAT ...		
<i>Data</i>	<i>Type</i>	<i>Example</i>
Opcode	ControlToTable	GAME_SPECTATOR_SEAT
Spectator seat number	integer	3
Spectator name	string	spectator32

Description

A single spectator seat assignment or a change thereof is communicated by this message. The only difference to GAME_SEAT is that no seat type is sent.

Message Data

None

Usage

This message appears during the WAITING or PLAYING state.

GAME_CHAT**Name**

GAME_CHAT — Message from a player on the table

Synopsis

GAME_CHAT ...		
<i>Data</i>	<i>Type</i>	<i>Example</i>
Opcode	ControlToTable	GAME_CHAT
Player name	string	player99
Message	string	hello how are you?

Description

Message from a player on the table

Message Data

None

Usage

This message appears during the WAITING or PLAYING state.

GAME_STATS**Name**

GAME_STATS — Statistics about a player

Synopsis

GAME_STATS ...		
<i>Data</i>	<i>Type</i>	<i>Example</i>
Opcode	ControlToTable	GAME_STATS
ENTRYTBL not supported.		

Description

Statistics about a player

Message Data

None

Usage

This message appears during the WAITING or PLAYING state.

GAME_INFO

Name

GAME_INFO — Information about a seat

Synopsis

GAME_INFO ...		
<i>Data</i>	<i>Type</i>	<i>Example</i>
Opcode	ControlToTable	GAME_INFO
Number of seats	integer	1
ENTRYTBL not supported.		

Description

Detail information about a seat or about all seats is available. For registered players, photo URL and realname might be known to the server and are reported here. The hostname can be reported for all players and spectators, but in most cases will require their agreement to publish this data.

Message Data

None

Usage

This message appears during the WAITING or PLAYING state.

Messages from game client to core client

GAME_STATE

Name

GAME_STATE — Indicate state change

Synopsis

GAME_STATE ...		
<i>Data</i>	<i>Type</i>	<i>Example</i>
Opcode	TableToControl	GAME_STATE
State	GGZModState	STATE_WAITING

Description

Indicate state change

Message Data

None

Usage

This message appears during the WAITING or PLAYING state.

STAND

Name

STAND — Request to stand up from table and become spectator

Synopsis

STAND ...

<i>Data</i>	<i>Type</i>	<i>Example</i>
Opcode	TableToControl	STAND

Description

Request to stand up from table and become spectator

Message Data

None

Usage

This message appears during the WAITING or PLAYING state.

SIT

Name

SIT — Request to sit down and become a player again

Synopsis

SIT ...		
<i>Data</i>	<i>Type</i>	<i>Example</i>
Opcode	TableToControl	SIT
Seat number	integer	2

Description

Request to sit down and become a player again

Message Data

None

Usage

This message appears during the WAITING or PLAYING state.

BOOT

Name

BOOT — Boot a player from the table

Synopsis

BOOT ...		
<i>Data</i>	<i>Type</i>	<i>Example</i>
Opcode	TableToControl	BOOT
Player name	string	player56

Description

Boot a player from the table

Message Data

None

Usage

This message appears during the WAITING or PLAYING state.

BOT

Name

BOT — Request for a bot joining the table

Synopsis

BOT ...		
<i>Data</i>	<i>Type</i>	<i>Example</i>
Opcode	TableToControl	BOT
Seat number	integer	2

Description

Request for a bot joining the table

Message Data

None

Usage

This message appears during the WAITING or PLAYING state.

OPEN

Name

OPEN — Open up a previously reserved seat

Synopsis

OPEN ...		
<i>Data</i>	<i>Type</i>	<i>Example</i>
Opcode	TableToControl	OPEN
Seat number	integer	2

Description

Open up a previously reserved seat

Message Data

None

Usage

This message appears during the WAITING or PLAYING state.

CHAT

Name

CHAT — Send a chat message

Synopsis

CHAT ...		
<i>Data</i>	<i>Type</i>	<i>Example</i>
Opcode	TableToControl	CHAT
Message	string	hola todos

Description

Send a chat message

Message Data

None

Usage

This message appears during the WAITING or PLAYING state.

INFO

Name

INFO — Request seat or player information

Synopsis

INFO ...		
<i>Data</i>	<i>Type</i>	<i>Example</i>
Opcode	TableToControl	INFO
Seat number	integer	-1

Description

Request information about a specific seat, or about all seats. (All seats are returned if the seat number is -1.)

Message Data

None

Usage

This message appears during the WAITING or PLAYING state.

Symbolic identifiers and their values

ControlToTable

Name

`ControlToTable` — Opcodes from GGZ core client to the game client module

Synopsis

<i>Identifier</i>	<i>Value</i>	<i>Description</i>
GAME_LAUNCH	0	message
GAME_SERVER	1	message
GAME_SERVER_FD	2	message
GAME_PLAYER	3	message
GAME_SEAT	4	message
GAME_SPECTATOR_SEAT	5	message
GAME_CHAT	6	message
GAME_STATS	7	message
GAME_INFO	8	message

Description

All opcodes are of type integer.

TableToControl

Name

`TableToControl` — Opcodes from game client module to GGZ core client

Synopsis

<i>Identifier</i>	<i>Value</i>	<i>Description</i>
-------------------	--------------	--------------------

GAME_STATE	0	message
STAND	1	request
SIT	2	request
BOOT	3	request
BOT	4	request
OPEN	5	request
CHAT	6	request
INFO	7	request

Description

All opcodes are of type integer.

GGZSeatType

Name

GGZSeatType — Possible seat assignments for a table

Synopsis

<i>Identifier</i>	<i>Value</i>	<i>Description</i>
GGZ_SEAT_NONE	0	Not initialized yet (invalid)
GGZ_SEAT_OPEN	1	Initialized to open, will be filled later
GGZ_SEAT_BOT	2	Internal or external AI player
GGZ_SEAT_PLAYER	3	Human player
GGZ_SEAT_RESERVED	4	Reserved for AI or human player of a certain name

Description

All seat types are of type integer.

GGZModState

Name

GGZModState — Possible game states for a game client

Synopsis

<i>Identifier</i>	<i>Value</i>	<i>Description</i>
STATE_CREATED	0	...
STATE_CONNECTED	1	...
STATE_WAITING	2	...
STATE_PLAYING	3	...
STATE_DONE	4	...

Description

All states are of type integer.